

RPL Enterprises
(Go Flight Interface Module) GF-SECM

		DEVICE					INPUT					FUNCTION	
GoFlight Module	Pos.	X	ID	Enabled/	Import	Export	Input	Default	Default	Pos.	Input Event	Input	Custom
GF-SECS				Disabled				FSA	PMDG iFly	V		Action	Value
GF-SECS Module			0	Enabled	n/a	n/a							
Toggle Switches													
Bat							BUTTON_MASTER_BAT	YES		ON	sim/electrical/battery_1_on	NOTHING	0
Alt							BUTTON_MASTER_ALT	YES		ON	sim/electrical/generator_1_on	NOTHING	0
Avionics Master							BUTTON_MASTER_AVIONICS	YES		ON	sim/systems/avionics_on	NOTHING	0
Fuel Pump							BUTTON_FUEL_PUMP	YES		ON	sim/fuel/fuel_pumps_on	NOTHING	0
Carb Heat							BUTTON_CARB_HEAT	YES		ON	sim/engines/carb_heat_on	NOTHING	1
Pitot Heat							BUTTON_PITOT_HEAT	YES		ON	sim/ice/pitot_heat0_on	NOTHING	0
Panel							BUTTON_PANEL_LIGHTS	YES		ON	sim/none/none	NOTHING	0
Beacon							BUTTON_BEACON_LIGHTS	YES		ON	sim/lights/beacon_lights_on	NOTHING	0
Nav							BUTTON_NAV_LIGHTS	YES		ON	sim/lights/nav_lights_on	NOTHING	0
Strobe							BUTTON_STROBE_LIGHTS	YES		ON	sim/lights/strobe_lights_on	NOTHING	0
Taxi							BUTTON_TAXI_LIGHTS	YES		ON	sim/lights/taxi_lights_on	NOTHING	0
Landing							BUTTON_LANDING_LIGHTS	YES		ON	sim/lights/landing_lights_on	NOTHING	0
Cowl Flaps							BUTTON_COWL	YES		ON	sim/none/none	NOTHING	0
Flaps Down							BUTTON_FLAPS_DOWN	YES		ON	sim/flight_controls/flaps_up	NOTHING	0
Flaps Up							BUTTON_FLAPS_UP	YES		ON	sim/flight_controls/flaps_down	NOTHING	0
Gear							BUTTON_GEAR	YES		ON	sim/flight_controls/landing_gear_up	NOTHING	0
Rotary SW							Selector_Engine						
OFF										1	sim/magnetos/magnetos_off_1	NOTHING	0
MAG L										2	sim/magnetos/magnetos_right_1	NOTHING	0
MAG R										3	sim/magnetos/magnetos_left_1	NOTHING	0
MAG BOTH										4	sim/magnetos/magnetos_both_1	NOTHING	0
START										5	sim/starters/engage_starter_1	REPEAT	0

RPL Enterprises
(Go Flight Interface Module) GF-SECM

		DEVICE				NS		
GoFlight Module	Pos.	X	ID	Enabled/	Import	Sync Data	Sync Action	Sync
GF-SECS				Disabled				Value
GF-SECS Module			0	Enabled	n/a			
Toggle Switches								
Bat						sim/cockpit/electrical/battery_on	OFF	0
Alt						sim/cockpit/electrical/generator_on[1]	ON	1
Avionics Master						sim/cockpit/electrical/avionics_on	ON	1
Fuel Pump						sim/cockpit/engine/fuel_pump_on[0]	ON	1
Carb Heat						sim/flightmodel/engine/ENGN_heat[0]	ON	1
Pitot Heat						sim/cockpit/switches/pitot_heat_on	ON	1
Panel							NOTHING	0
Beacon						sim/cockpit/electrical/beacon_lights_on	ON	1
Nav						sim/cockpit/electrical/nav_lights_on	ON	1
Strobe						sim/cockpit/electrical/strobe_lights_on	ON	1
Taxi						sim/cockpit/electrical/taxi_light_on	ON	1
Landing						sim/cockpit/electrical/landing_lights_on	ON	1
Cowl Flaps							NOTHING	0
Flaps Down							NOTHING	0
Flaps Up							NOTHING	0
Gear						sim/aircraft/parts/acf_gear_deploy[0]	ON	1
Rotary SW								
OFF						Nil	NOTHING	0
MAG L						Nil	NOTHING	0
MAG R						Nil	NOTHING	0
MAG BOTH						Nil	NOTHING	0
START						Nil	NOTHING	0